

A1

GOOD PRACTICE FOR
WILDING CONIFER CONTROL



**PREVENT
THE SPREAD**

National Wilding Conifer Control Programme

GROUND-BASED HERBICIDE INJECTION – ‘DRILL AND FILL’

VERSION 1: OCTOBER 2019

Drill & Fill can be a very cost-effective method where trees have a trunk diameter over 10cm and are accessible to ground crews.

CONTENTS

ABOUT THIS DOCUMENT	3
VERSION CONTROL	3
1. DRILL AND FILL MATERIALS	4
1.1 Delivery equipment and set up	4
2. HERBICIDE CHOICE AND USAGE	5
3. DRILL AND FILL METHOD	6
3.1 Best time of year to drill and fill	6
3.2 Method	6

Photograph front cover: Drill and fill method in action, Marlborough Sounds area. (Photo source: A. Macalister)

ABOUT THIS DOCUMENT

Overall disclaimer:	<p>The information in this publication represents the collective view of the National Wilding Conifer Control Programme (the 'National Programme'). We have made every effort to ensure the information is accurate. However, the National Programme does not accept any responsibility or liability for error of fact, omission, interpretation or opinion, nor for the consequences of any decisions based on this information.</p> <p>Good practice use by any reader is done so at their own risk, and the National Programme rejects all liability for any risk or loss as a result of applying this good practice information.</p>
Acknowledgements:	We thank the Department of Conservation, R&D Environmental Ltd and Central Otago Wilding Conifer Control Group for sharing their knowledge and expertise.
Principal author:	Biosecurity New Zealand (Ministry for Primary Industries)
Document Owner:	Wilding Conifer Programme Manager, Biosecurity New Zealand (Ministry for Primary Industries)
Approved for distribution and use:	Operations Advisory Group, Technical Advisory Group (National wilding conifer program)
Last reviewed:	11 October 2019
Classification / status:	[Version 1]
Document reference:	[Good – Practice & Drill and Fill V1 October 19]
All comments and suggestions for good practice improvement	Email to: wildingconifers@mpi.govt.nz

VERSION CONTROL

Date	Details	Document ID and version no.	Amended by
October 2019	Draft finalised and published	Version 1	
1 July 2020	Additional safety notes for Tordon pasture boss or equivalent (360 G/L Triclopyr amine + 30 G/L aminopyralid).	Version 2	MPI

This document should be read in conjunction with:

WorkSafe - Working safely with chemicals and fuels on farms

WorkSafe - HSNO codes of practice for hazardous substances

1. DRILL AND FILL MATERIALS

1.1 EQUIPMENT RECOMMENDATIONS

Below are recommendations for equipment for set-up and delivery.

EQUIPMENT TYPE	RECOMMENDATIONS	IMPORTANT CONSIDERATIONS
Drilling	<ul style="list-style-type: none">• 18 V drill with a 13–18 mm wood bit or auger.• Petrol-powered mechanised drill (fitted with a 20 mm auger bit).	Petrol-powered drills should not be used in environments where there is a fire risk.
Application	<ul style="list-style-type: none">• A bottle fitted with a nozzle• A backpack applicator (to be used where conditions allow)	Bottles must be labelled. Backpack applicator should only be used where open conditions allow. All application equipment must comply with the Health and Safety at Work (Hazardous Substances) Regulations 2017.
Personal Protective Equipment (PPE)	<ul style="list-style-type: none">• Safety glasses (used when using Metsulfuron Methyl or Glyphosate)• Chemical goggles (used when using neat Tordon Pasture boss or equivalent (360 g/L triclopyr amine + 30 g/L aminopyralid))• Chemical gloves (> 14 mils)• Cotton overalls (buttoned to the neck and wrist)• Waterproof boots	Personal Protective Equipment (PPE) must be used in handling, mixing, application and cleaning of herbicides and associated equipment. See the Safety Material Data Sheet.
Other	<ul style="list-style-type: none">• A spill kit with a minimum capacity of 20-litre• A 400g fire extinguisher (in high• A First Aid kit with saline eye wash must be available for operators	Wherever the fire risk is above 'Low' on the Fire Danger Class System, fire extinguishers must be used.

2. HERBICIDE CHOICE AND USAGE

2.1 TRAINING

Employers have a duty to train employees (or make sure someone who is trained supervises them) so they can do their work safely. The Site Lead (or equivalent role as named in the relevant HSMP) for a drill and fill operation must make sure that everyone using chemicals is appropriately trained.

Note, a GROWSAFE standard certification is needed for any worker using neat Tordon Pasture boss or equivalent (360 g/L triclopyr amine + 30 g/L aminopyralid).

2.2 RECOMMENDED HERBICIDE

Before application refer to and follow the directions of the products Safety Material Data Sheet.

	METSULFURON METHYL	GLYPHOSATE	TRICLOPYR AMINE + AMINOPYRALID
Situation of Use	All wilding conifer species except for <i>Pinus contorta</i> .	When Metsulfuron methyl is not available. For all wilding conifer species except for <i>Pinus contorta</i> .	Only for control of control of <i>Pinus contorta</i> .
Recommended Mixing	50g of Associate or equivalent (600 g/kg metsulfuron-methyl* formulation) per litre of clean water (pH > 7).	Undiluted product (450-510 ml/L).	Neat Tordon Pasture boss or equivalent (360 g/L triclopyr amine + 30 g/L aminopyralid).

2.3 SAFETY NOTES FOR TORDON PASTURE BOSS OR EQUIVALENT

Exposing the eye to Tordon Pasture boss or equivalent can cause serious damage/irritation and in extreme cases, may result in permanent impairment of vision, even blindness.

In the instance of drill and fill, Tordon Pasture boss or equivalent is used neat and there is an increased risk of exposure. As a result, drill and fill operations that involve neat Tordon Pasture boss or equivalent should be carried out by experienced operators with current GROWSAFE standard certificates. The Site Lead (or equivalent role as named in the relevant HSMP) for each drill and fill operation is responsible for ensuring all operators using neat Tordon Pasture boss or equivalent hold this certification.

Care must be taken at all times to protect eyes when handling neat Tordon Pasture boss or equivalent. This means:

- a. bottles or applicators must be stored and carried in a way that minimises the risk of accidental spilling or spurting of chemical,
- b. chemical goggles, sealed goggles or a full face mask must be worn when handling the chemical, and
- c. an eye wash station (portable or in a vehicle) must be at most available (i.e. no more than 5 minutes away) to the operator using neat Tordon Pasture boss or equivalent at all times.



3. DRILL AND FILL METHOD

3.1 BEST TIME OF YEAR TO DRILL AND FILL

The best time to drill and fill is during active growing conditions, typically between September and February each year.

3.2 METHOD

HOLE NUMBER AND DEPTH

The number of holes drilled depends on the size of diameter at breast height (DBH), herbicide mix used, and the wider surrounds of the tree.

Table 1: The recommended number of holes to DBH measurement for different tree species.

SIZE THRESHOLDS DBH (CM)		10	20	25	35	50	80	100	105	110	120	125	135	140	160
Number of holes to be drilled for each herbicide mix	1. Metsulfuron methyl	1	1	1	1	1	1	1	1	1	1	2	2	2	2
	2. Glyphosate	1	1	2	3	4	6	8	8	8	9	10	11	12	13
	3. Triclopyramine + aminopyralid	1	2	2	3	3	3	3	4	4	4	4	4	4	4

Important considerations:

- On Multi-stem trees, each stem should be treated as a separate tree.
- When the tree to be controlled sits in open area and therefore, likely to have more foliage an additional two holes per tree should be added to the recommended number

DRILLING

Holes should be drilled at even spaces around the trunk to ensure an even distribution of the chemical throughout the tree.

Holes should be drilled into the base of the tree or prominent feeder roots as near to the ground as possible, while still being safe (a comfortable height to work at for long periods).

The holes should be drilled:

- on a downward angle (approx. 45° down), and
- slightly out (30° from the horizontal cross section) , and
- to a depth of 4 cm deep (excluding bark) and no more than 8cm.

HERBICIDE APPLICATION

The hole should be filled with 10mls of the herbicide immediately after drilling. The herbicide should reach up to the cambium layer at the outer edge of the sapwood. It is not necessary to plug the holes after filling as the hole is drilled at a slight downward angle.

GPS RECORDING

The location of all trees treated should be recorded as a GPS waypoint so that treated trees can be relocated to accurately assess the success of the control operation.